MULTICS SYSTEM-PROGRAMMERS MANUAL

SECTION BN.7.08 PAGE 1

Published: 04/21/67

Identification

Data segment grower datmk_ N. Adleman, D.H. Johnson

Purpose

This section describes the datmk_procedure which is used to create data segments as they are required during the execution of a process. In particular, datmk_is used in the implementation of the PL/I static storage feature. Datmk_is called by the linker as a result of an out-reference in a Tinkage section with the "trap before link" option (MSPM BD.7.01).

By the time the faulting instruction has finished executing, the data segment has been created or grown and, possibly, initialized, and the user's instruction has had its desired effect.

Usage

Use of datmk is specified in EPLBSA by:

	segref segref	<pre>datmk_,datmk_ segment,symbol(datmk_(arglist))</pre>
arglist	dec dec arg	size initialswitch initializer

Here <u>segment</u> and <u>symbol</u> are the names of a segment and an in-reference in that segment's linkage section. At execution time, the first reference to <u>symbol</u>, e.g. the instruction

eapbp symbol

causes a trap to the linker, which in turn calls datmk_. If <u>seqment</u> is not active in the process, datmk_ creates it, including its linkage section. Then, if <u>symbol</u> is not listed as an in-reference in <u>seqment's</u> linkage section, datmk_ grows <u>segment</u> by <u>size</u> words and creates the in-reference pointing to the newly-grown storage. MULTICS SYSTEM-PROGRAMMERS MANUAL

If <u>initialswitch</u> is non-zero, datmk fills in the faulting link pair and calls the user's initializing procedure located at <u>initializer</u>. This call has the form of a call to a PL/I internal procedure (see BP. 3.00 for details) with no arguments. Since this call does not go through the linkage section, if the initializing routine uses the base pair lb if the initializing routine uses the base pair lb if the initializing the proper values itself. Assuming that lb is properly set, however, the initializing routine may freely refer to symbol.

In EPL, datmk_ is called as follows:

call datmk (argpointer, panelpointer);

where <u>argpointer</u> is a pointer to the user's argument list specified in the <u>segref</u> pseudo-op, and <u>panel</u> is a pointer to stored machine conditions as follows:

words 1-8 contain the base address registers 9-16 contain the arithmetic registers 17-23 contain the SCU information

Method

When datmk is called, it performs the following steps:

- 1. References to <u>segment</u> and <u>symbol</u> are established by building pointers to the character strings in the linkage section of the process that called datmk_.
- 2. With the "trap before definition" allowed, the generate_ptr procedure (MSPM BY.13.02) is called to determine the status of segment and symbol.
- 3. If the symbol is already defined, datmk_returns control directly to its caller, with no further action. If the symbol is not defined, and the segment is known to the calling process, control continues at step 4. Otherwise, the segment is created by the <u>setnamestatus</u> procedure which sets the Segment Name Table and retrieves the segment pointer. The new segment is created so that any user requiring a segment named <u>segment</u> has access (global access). The first word of the newly created segment is set to zero. Note that the first word of all data segments is reserved to

MULTICS SYSTEM-PROGRAMMERS' MANUAL SECTION BN.7.08 PAGE 3

contain a value which represents the size, in words, of the data segment.

4. The link_change\$make definition procedure is called to insert a definition for symbol in the linkage section of the calling process. The contents of the first word of <u>segment</u> is used as the value <u>argument</u> to the link_change\$make_ definition procedure.

- 5. The first word of <u>segment</u> is then incremented by the value of the <u>size</u> argument to datmk. In effect, <u>segment</u> is "grown" by size words.
- 6. If there was only one argument to datmk_, (i.e. initialswitch is zero), control returns to the calling process. Otherwise, to force a link (fill-in the faulting pair), the link fault\$force procedure is called with the "trap before link" option ignored. Then, the caller's initializing routine, as specified by the <u>initializer</u> argument, is called to initialize the data segment. This is done by accessing the sb _ sp information in the argument list to datmk. When control is returned to datmk_ by the user's initializing routine, datmk_ returns complete control to the calling process.

Errors

The datmk_procedure uses the standard error handling mechanism (MSPM BY.11) to report all abnormalities that it encounters. The condition "datmk_" is signalled for the following errors:

Error No.	Meaning
1	error determining if the segment is known to the calling process
2	an incorrect value of "class" was returned by generate_ptr
3	error attempting to create the segment
14	error attempting to make a symbol definition
5	error attempting to force a link